# cisco.



## Firepower REST API Quick Start Guide, Version 6.1

First Published: Last Modified:

#### Americas Headquarters Cisco Systems, Inc.

Cisco Systems, Inc. 170 West Tasman Drive San Jose, CA 95134-1706 USA http://www.cisco.com Tel: 408 526-4000 800 553-NETS (6387) Fax: 408 527-0883 THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: http:// WWW.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

© 2016 Cisco Systems, Inc. All rights reserved.



CONTENTS

CHAPTER 1	About the Firepower REST API 1
	About the Firepower REST API 1
	Enabling the REST API 1
	Best Practices 2
CHAPTER 2	About the API Explorer <b>3</b>
	About the API Explorer <b>3</b>
	Authentication to the API Explorer <b>3</b>
	Logging into API Explorer 4
	Setting the Domain 4
	Obtaining Sample Code 4
	Obtaining Sample Code 5
	Viewing API Parameters 5
CHAPTER 3	Connecting with a Client 7
	Authentication from a REST API Client 7
	Requesting an Authentication Token 8
	Refreshing an Authentication Token <b>9</b>
CHAPTER 4	Objects in the REST API 11
	Request Structure 11
	Response Structure <b>13</b>
	Rate Limiting 14
	Audit Services 14
	GET auditrecords 14
	Deployment Services 15
	GET deployabledevices 15

Γ

Device Group Services 15 DELETE devicegrouprecords 15 PUT devicegrouprecords 15 POST devicegrouprecords 15 GET devicegrouprecords 16 Device Services 16 DELETE devicerecords 16 PUT devicerecords 16 POST devicerecords 16 GET devicerecords 17 PUT fpphysicalinterfaces 17 GET fpphysicalinterfaces 17 DELETE fplogicalinterfaces 17 PUT fplogicalinterfaces 18 POST fplogicalinterfaces 18 GET fplogicalinterfaces 18 **DELETE inlinesets** 18 PUT inlinesets 18 POST inlinesets 19 GET inlinesets 19 DELETE virtualswitches 19 PUT virtualswitches 19 POST virtuals witches 20 GET virtualswitches 20 GET fpphysicalinterfaces 20 GET physicalinterfaces 20 GET bridgegroupinterfaces 21 GET redundantinterfaces 21 GET etherchannelinterfaces 21 GET subinterfaces 22 GET fpinterfacestatistics 22 Object 22 GET anyprotocolportobjects 22 GET application categories 22 GET applicationfilters 23

GET applicationproductivities 23

GET applicationrisks **23** 

GET applications 23

GET applicationtags 24

GET application types 24

GET continents 24

GET countries 24

GET endpointdevicetypes 25

GET geolocation 25

DELETE hosts 25

PUT hosts 25

POST hosts 25

GET hosts 26

DELETE icmpv4objects 26

PUT icmpv4objects 26

POST icmpv4objects 26

GET icmpv4objects 26

DELETE icmpv6objects 27

PUT icmpv6objects 27

POST icmpv6objects 27

GET icmpv6objects 27

GET is esecurity group tags 27

GET networkaddresses 28

DELETE networkgroups 28

PUT networkgroups 28

POST networkgroups 28

GET networkgroups 28

DELETE networks 29

PUT networks 29

POST networks 29

GET networks 29

DELETE portobjectgroups 29

PUT portobjectgroups 30

POST portobjectgroups 30

GET portobjectgroups 30

GET ports 30 DELETE protocolportobjects 30 PUT protocolportobjects 31 POST protocolportobjects 31 GET protocolportobjects 31 DELETE ranges 31 PUT ranges 31 POST ranges 32 GET ranges 32 GET realms 32 GET realmusergroups 32 GET realmusers 33 GET security grouptags 33 DELETE securityzones 33 PUT securityzones 33 POST securityzones 34 GET securityzones 34 GET siurlfeeds 34 GET siurllists 34 GET tunneltags 34 GET urlcategories 35 DELETE urlgroups 35 PUT urlgroups 35 POST urlgroups 35 GET urlgroups 35 DELETE urls 36 PUT urls 36 POST urls 36 GET urls 36 GET variablesets 36 DELETE vlangrouptags 37 PUT vlangrouptags 37 POST vlangrouptags 37 GET vlangrouptags 37 DELETE vlantags 37

1

I

PUT vlantags 38 POST vlantags 38 GET vlantags 38 Policy Services 38 DELETE accesspolicies 38 PUT accesspolicies 39 POST accesspolicies 39 GET accesspolicies 39 **DELETE accessrules** 39 PUT accessrules 39 POST accessrules 40 GET accessrules 40 PUT defaultactions 40 GET defaultactions 40 GET filepolicies 41 GET intrusionpolicies 41 GET snmpalerts 41 GET syslogalerts 41 Policy Assignment Services 42 PUT policyassignments 42 POST policyassignments 42 GET policyassignments 42 Status Services 42 GET taskstatuses 42 System Information 43 GET serverversion 43 Services Available in Firepower Threat Defense 43 GET physicalinterfaces 43 GET redundantinterfaces 43 GET etherchannelinterfaces 44 GET subinterfaces 44 GET bridgegroupinterfaces 44 POST devicerecords 44 PUT devicerecords 45 GET devicegrouprecords 45

- DELETE devicerecords **45**
- POST devicegrouprecords 45
- PUT devicegrouprecords 45
- GET devicegrouprecords 46
- DELETE devicegrouprecords 46
- POST securityzones 46
- PUT securityzones 46
- GET securityzones 46
- DELETE securityzones 47
- POST policyassignments 47
- PUT policyassignments 47
- GET policyassignments 47
- GET deployabledevices 47
- POST deployment requests 48



#### CHAPTER

## **About the Firepower REST API**

The Firepower REST API provides a lightweight API to manage a Firepower Management Center.

- About the Firepower REST API, page 1
- Enabling the REST API, page 1
- Best Practices, page 2

## **About the Firepower REST API**

With the release of Cisco's Firepower REST API, you now have light-weight, easy-to-use option for managing Firepower Threat Defense and legacy Firepower devices through a Firepower Management Center.

The REST API is an application programming interface (API), based on "RESTful" principles, which you can quickly enable on any Firepower Management Center running version 6.1 or higher, and use with a REST client.

After installing a REST client, you can contact the specific Firepower Management Center's REST agent and use standard HTTP methods to access current configuration information, and issue additional configuration parameters.

## Enabling the REST API

In Firepower Management Center, the REST API is enabled by default. However, if you are intending to use the REST API, you should confirm that it is enabled.

If you are using UCAPL mode, check that the REST API is not enabled.

#### Procedure

Step 1	Navigate to System>Configuration>REST API Preferences>Enable REST API
Step 2	Check the "Enable REST API" checkbox.
Step 3	Click "Save". A box saying "Save Successful" will display when the REST API is enabled.

## **Best Practices**

Cisco recommends the following best practices for optimal results with the REST API:

- Keep UI users and script users separate. Especially do not use the admin account as an API user.
- Do not give script users more privilege than needed.
- Always validate the content coming from the server.
- Validate/sanitize JSON content, as it may include embedded executable code.
- If you are using UCAPL mode you should disable REST API access to the Firepower Management Center



## **About the API Explorer**

- About the API Explorer, page 3
- Authentication to the API Explorer, page 3
- Obtaining Sample Code, page 4
- Viewing API Parameters, page 5

## **About the API Explorer**

The API Explorer provides a limited interface for the REST API as well as giving a view of the abilities of the REST API.

The API Explorer resides on the Firepower Management Center, and can be accessed via the Firepower Management Center at:

https://<management\_center\_IP\_or\_name>:<https\_port>/api/api-explorer

This explorer provides the list of APIs available on the Firepower Management Center, and their details.

## **Authentication to the API Explorer**

The REST API relies on the same authentication as the Firepower Management Center. Each function in the REST API maps to permissions in the Firepower Management Center.

You can log into the API Explorer using any account on the Firepower Management Center, but you will only be able to perform the functions for which the account has permissions. For more information on setting permissions for user roles, see the *Firepower Management Center Configuration Guide*.

The first time you connect to the API Explorer you may receive an error that the connection is not secure due to an invalid certificate. You will need to add an exception in your browser to use the certificate and accept the connection.

#### Logging into API Explorer

The REST API uses the same authentication and permission model as the Firepower Management Center. See the *Firepower Management Center Configuration Guide* for more information.

#### **Before You Begin**

Make sure you have an account on your Firepower Management Center with the required permissions to perform the tasks you want to perform using the REST API.

#### Procedure

- Step 1 Navigate to the following URL: https://<management\_center\_IP\_or\_name>:<https\_port>/api/api-explorer
- Step 2 Log in with your username and password and click "Sign In"

#### What to Do Next

Locate the desired resource and request.

#### Setting the Domain

The REST API can perform functions globally, in the default domain, or in specific domains.

#### **Before You Begin**

You must have a configured Firepower Management Center, an account with permissions to access the REST API in one or more domains configured on your FMC.

#### Procedure

In the upper right, drop down the **Domains** menu and select the desired domain.

#### What to Do Next

Locate the desired resource and request type.

## **Obtaining Sample Code**

You can use the Export Operation button in API Explorer to save the displayed method example as a Python or Perl script file to your local host. This script can be used to make that REST call, and can be integrated into your application. This is meant primarily as an educational and bootstrapping tool.

- Python: The Python scripts require you to install Python, available from https://www.python.org/. Once you've installed Python, you can run your script with python script.py username password.
- Perl: Using the Perl scripts requires some additional set-up-you need five components:

- Perl package, found at http://www.perl.org/
- Bundle::CPAN, found at http://search.cpan.org/~andk/Bundle-CPAN-1.861/CPAN.pm
- REST::Client, found at http://search.cpan.org/~mcrawfor/REST-Client-88/lib/REST/Client.pm
- MIME::Base64, found at http://perldoc.perl.org/MIME/Base64.html
- JSON, found at http://search.cpan.org/~makamaka/JSON-2.90/lib/JSON.pm

#### **Obtaining Sample Code**

The API Explorer can create sample code in Python and Perl to aid in creating a REST API client.

#### **Before You Begin**

You must have a configured Firepower Management Center and an account on that center with the permissions required to use the desired REST API functions.

#### Procedure

- **Step 1** Select the resource where you want to obtain sample code from the API INFO menu.
- Step 2 Locate the desired function and select DELETE, PUT, POST, or GET.
- **Step 3** Select and input all other parameters for the desired function. This will vary depending on the function.
- **Step 4** On the right, drop down the menu for "Export operation in" and select "Python script" or "Perl script".
- **Step 5** The sample code will pop up in a new window. Cut and paste this code to use in your REST API client.

#### What to Do Next

Use this sample code to implement your own REST API client.

## **Viewing API Parameters**

Each resource has a set of parameters and fields associated with it. You can view the parameters and fields by performing any of the supported operations for that resource within API Explorer.

#### **Before You Begin**

You must have a configured Firepower Management Center and an account on that center with the permissions required to use the desired REST API functions.

1

#### Procedure

- **Step 1** Select the desired resource.
- **Step 2** Select one of the supported operations for that resource.



## **Connecting with a Client**

You can access the REST API using any REST API client. Typically REST API clients are available as browser plugins, but any REST API client is allowed.

Note

If connecting to the REST API for the first time, you will receive a certificate warning. You need to accept the certificate in order to use the REST API.

• Authentication from a REST API Client, page 7

## **Authentication from a REST API Client**


**Cisco recommends that you use different accounts for interfacing with the API and the Firepower User Interface.** Credentials cannot be used for both interfaces simultaneously, and will be logged out without warning if used for both.

The first time you connect to the REST API you may receive an error that the connection is not secure due to an invalid certificate. Add an exception in your browser to use the certificate and accept the connection.

With Token Based Authentication you obtain a token by providing your username and password. You use this token to access an HTTP service for a limited time period without the need for the username and password with every request. In other words, to eliminate the need for authenticating with your username and password with each request, you replace user credentials with a uniquely generated access token, which you use for accessing resources for up to 30 minutes and can refresh up to three times.

The diagram below illustrates the concept of token-based authentication:

I



#### **Token-Based Authentication**

### **Requesting an Authentication Token**

The Token Generation Utility provides an authentication token which can be used in your REST API client.

#### **Before You Begin**

You must have a configured Firepower Management Center and an account on that center with credentials to use the REST API. You must also have a REST API Client which can perform basic authentication.

#### Procedure

- **Step 1** Open your REST API Client.
- **Step 2** Set the client to make a POST command to the following URL: https://<management\_center\_IP\_or\_name>/api/fmc\_platform/v1/auth/generatetoken.
- **Step 3** Include the username and password as a basic authentication header. The POST body should be blank.

#### What to Do Next

Add the header X-auth-access-token:<authentication token value> in requests to the API.

Add the headers X-auth-access-token:<authentication token value> and X-auth-refresh-token:<refresh token value> in requests to refresh the token as described in Refreshing an Authentication Token, on page 9

### **Refreshing an Authentication Token**

Firepower Management Center REST API authentication tokens are valid for 30 minutes, and can be refreshed up to three times.

#### **Before You Begin**

Obtain valid authentication and refresh tokens from the Firepower Management Center REST API. Ensure these tokens have been refreshed less than three times.

#### Procedure

**Step 1** Open your REST API Client.

Step 2 Set the client to make a POST command to the following URL: https://<management\_center\_IP\_or\_name>/api/fmc\_platform/v1/auth/refreshtoken with the headers X-auth-access-token:<authentication token value> and X-auth-refresh-token:<refresh token value>.

#### What to Do Next

Add the header X-auth-access-token:<new authentication token value> in requests to the API.

Add the header X-auth-refresh-token:<new refresh token value> in requests to refresh the token.

٦



#### CHAPTER

## **Objects in the REST API**

- Request Structure, page 11
- Response Structure, page 13
- Rate Limiting, page 14
- Audit Services, page 14
- Deployment Services, page 15
- Device Group Services, page 15
- Device Services, page 16
- Object, page 22
- Policy Services, page 38
- Policy Assignment Services, page 42
- Status Services, page 42
- System Information, page 43
- Services Available in Firepower Threat Defense, page 43

## **Request Structure**

I

Request Structure:

Requests are sent to the Firepower Management Center as HTTPS requests with the Uniform Resource Identifier (URI) of the form described below:

https://<management\_center\_IP\_or\_name>:<https\_port>/<object\_URL>/object\_UUIDoptions
Where:

- <management\_center\_IP\_or\_name> is the IP address or Fully Qualified Domain Name of the Firepower Management Center
- <https\_port> is the port number used by the Firepower Management Center for HTTPS connections. This port is always 443.
- object\_URL>

is the specific URL for the desired resource. These URLs are unique for each resource and are given below.

• options

are the options given with the request. Options can be used to modify the output and filter results.

• {UUID}

Many URLs contain one or more UUIDs which must be specified. Most URLs include the domain UUID, which can be found in the API Explorer. When deleting or modifying an object, or requesting information about a specific object, the URL will end with the object UUID.

Available request methods are:

- GET
- Retrieves data from the specified object. GET is a read-only operation.
- PUT

 Adds the supplied information to the specified object; returns a 404 Resource Not Found error if the object does not exist.



Currently PUT may be used to create a new object, but this ability may be removed in later releases. Use POST to create new objects and PUT to modify existing objects.

```
• POST
```

- Creates the object with the supplied information.

- DELETE
- Deletes the specified object.
- PATCH
- Not supported.

The API supports query parameters for almost all requests. For GET requests, the following query parameters can be used to control the number of of returned objects and the pagination:

expanded

- This is a True/False value which indicates whether you get a full listing of an item in a list or only a reference.

• offset

- Indicates the position in the list where you want to start.

• limit

- Indicates the number of items you want to retrieve in a page.

The API supports filtering on the basis of query parameters passed with a request. Filtering can be done based on specific attributes in a model. The parameters available for filtering vary by object, and are listed with the request below.

## **Response Structure**

Note

The REST API will only serve 25 results per page. This can be increased up to 1000 using the limit query parameter.

The response structure can be:

- LOCATION Newly created resource ID; for POST only—holds the new resource ID (as a URI representation).
- CONTENT-TYPE Media type describing the response message body; describes the representation and syntax of the response message body.
- Each response includes an HTTP status or error code. Available codes fall into these categories:
- 20x A two-hundred series code indicates successful operation, including:
- 200 OK
- Standard response for successful requests.
- 201 Created

- Request completed; new resource created.

• 202 Accepted

- Request accepted, but processing not complete.

• 204 No Content

- Server successfully processed request; no content is being returned.

- 4xx A four-hundred series code indicates a client-side error, including:
- 400 Bad Request
- Invalid query parameters, including unrecognized parameters, missing parameters, or invalid values.
- 404 Not Found

- The provided URL does not match an existing resource. For example, an HTTP DELETE may fail because the resource is unavailable.

• 405 Method not Allowed

- An HTTP request was presented that is not allowed on the resource; for example, a POST on a read-only resource.

• 429 Too Many Requests

- Too many requests were sent to the API. This error will occur if you send more than 120 requests per minute.

• 5xx - A five-hundred series code indicates a server-side error.

In the case of an error, in addition to the error code, the return response may include an error object containing more details about the error. The JSON error/warning response schema is as follows:

```
[
{ "code" : "string",
  "details": "string",
  "context": attribute name,
  "level" : <Error/Warning/Info>
  },
...
]
```

where the object properties are:

#### **Table 1: Object Properties**

Property	Туре	Description
messages	List of Dictionaries	List of error or warning messages
code	String	Error/Warning/Info code
details	String	Detailed message corresponding to Error/Warning/Info

## **Rate Limiting**

The Firepower REST API implements rate limiting to reduce network load.

The API will accept no more than 120 messages in a minute. It will only allow 10 simultaneous connections per IP address. These are not configurable parameters.

If a client exceeds these limits, the API will give an HTTP 429 error.

## **Audit Services**

### **GET** auditrecords

Request Type: **GET** Description: Retrieves audit records. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/audit/auditrecords Permissions: System > Monitoring > Audit Parameters available for filtering: username, subsystem, source, starttime, endtime

## **Deployment Services**

### **GET deployabledevices**

#### Request Type: GET

Description: Retrieves list of all devices with configuration changes, ready to be deployed. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/deployment/deployabledevices Permissions: Deploy Configuration to Devices Parameters available for filtering: name

### **POST deploymentrequests**

#### Request Type: POST

Description: Creates a request for deploying configuration changes to the specified device. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/deployment/deploymentrequests/{object\_UUID} Permissions: Deploy Configuration to Devices

## **Device Group Services**

### **DELETE devicegrouprecords**

Request Type: DELETE

Description: Deletes a device group with the specified object ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

### **PUT devicegrouprecords**

Request Type: PUT

Description: Modifies a device group with the specified object ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

## **POST devicegrouprecords**

I

Request Type: POST

Description: Create a device group with the specified object ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords Permissions: Devices > Device Management > Modify Devices

### **GET devicegrouprecords**

Request Type: GET

Description: Retrieves the device group associated with the specified ID. If no ID is specified, retrieves list of all device groups.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID}

Permissions: Devices > Device Management > View Devices

## **Device Services**

#### **DELETE devicerecords**

Request Type: DELETE

Description: Unregisters the specified device. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

### **PUT devicerecords**

Request Type: PUT

Description: Modifies the device record associated with the specified ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

#### **POST devicerecords**

Request Type: POST

Description: Registers the specified device to the Firepower Managemenr Center. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords Permissions: Devices > Device Management > Modify Devices

#### **GET** devicerecords

#### Request Type: GET

Description: Retrieve device information. If a device ID is specified, the information for the specificed device is retrieved. If no ID is specified, retrieves information for all devices.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: hostName

### PUT fpphysicalinterfaces

Request Type: PUT

Description: Modify a physical interface on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/ fpphysicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

#### **GET** fpphysicalinterfaces

Request Type: GET

Description: Retrieves information on the physical interface associated with the specified NGIPS device ID and interface ID. If no ID is specified, retrieves list of all physical interfaces associated with the specified NGIPS device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fpphysicalinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fpphysicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

## **DELETE** fplogicalinterfaces

Request Type: DELETE

Description: Delete logical interfaces on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/ fplogicalinterfaces/{object\_UUID}

Permissions: Device > Device Management > Modify Device

#### **PUT fplogicalinterfaces**

#### Request Type: PUT

Description: Modify a logical interface on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fplogicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

#### **POST fplogicalinterfaces**

Request Type: POST

Description: Creates logical interfaces on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fplogicalinterfaces

Permissions: Devices > Device Management > Modify Device

### **GET** fplogicalinterfaces

#### Request Type: GET

Description: Retrieves the logical interface associated with the specified NGIPS device ID and interface ID. If no ID is specified, retrieves list of all logical interfaces associated with the specified NGIPS device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fplogicalinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fplogicalinterfaces/{obect\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

### **DELETE** inlinesets

Request Type: **DELETE** 

Description: Delete inline sets on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/inlinesets/ {object\_UUID}

Permissions: Device > Device Management > Modify Device

#### **PUT** inlinesets

Request Type: PUT

Description: Modify an inline set on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/inlinesets/ {object\_UUID}

Permissions: Device > Device Management > Modify Device

### **POST** inlinesets

Request Type: POST

Description: Creates inline sets on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/inlinesets

Permissions: Devices > Device Management > Modify Device

#### **GET** inlinesets

Request Type: GET

Description: Retrieves information on the inline set associated with the specified NGIPS device ID and inline set ID. If no inline set ID is specified, retrieves list of all inline sets associated with the specified NGIPS device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/inlinesets

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ inlinesets/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

### **DELETE virtualswitches**

Request Type: DELETE

Description: Delete a virtual switch on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/virtualswitches/ {object\_UUID}

Permissions: Device > Device Management > Modify Device

### **PUT virtualswitches**

Request Type: PUT

Description: Modify a virtual switch on the specified device.

URL: /api/fmc\_config/v1/domain/{UUID}/devices/devicerecords/{containerUUID}/virtualswitches/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

#### **POST virtualswitches**

#### Request Type: POST

Description: Create a virtual switch on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/virtualswitches

Permissions: Device > Device Management > Modify Device

### **GET** virtualswitches

Request Type: GET

Description: Retrieves virtual switch associated with the specified NGIPS device ID and virtual switch ID. If no virtual switch ID is specified, retrieves list of all virtual switches associated with the specified NGIPS device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/ virtualswitches

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/ virtualswitches/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

#### **GET** fpphysicalinterfaces

Request Type: GET

Description: Retrieves information on the physical interface associated with the specified NGIPS device ID and interface ID. If no ID is specified, retrieves list of all physical interfaces associated with the specified NGIPS device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fpphysicalinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ fpphysicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

#### **GET** physicalinterfaces

Request Type: GET

Description: Retrieves the physical interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all physical interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/physicalinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ physicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management

### **GET** bridgegroupinterfaces

Request Type: GET

Description: Retrieves the bridge group interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all bridge group interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ bridgegroupinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ bridgegroupinterfaces/{object\_UUID}

Permissions: Devices > Device Management

### **GET redundantinterfaces**

Request Type: GET

Description: Retrieves the redundant interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all redundant interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ redundantinterfaces

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ redundantinterfaces/{object\_UUID}

Permissions: Devices > Device Management

### **GET** etherchannelinterfaces

Request Type: GET

Description: Retrieves the ethernet channel interface associated with the specified NGFW device ID and interface ID. If no ID is specified, retrieves list of all ethernet channel interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ etherchannelinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ etherchannelinterfaces/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering:

#### **GET** subinterfaces

#### Request Type: GET

Description: Retrieves the sub-interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all sub-interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/subinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/ subinterfaces/{object\_UUID}

Permissions: Devices > Device Management

#### **GET** fpinterfacestatistics

Request Type: GET

Description: Retrieves list of statistics for all interfaces associated with the specified NGIPS device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/ devicerecords/{container\_UUID}/ fpinterfacestatistics

Permissions: Devices > Device Management

Parameters available for filtering: name

## **Object**

### **GET** anyprotocolportobjects

Request Type: GET

Description: Retrieves the any protocol port object associated with the specified ID. If no ID is specified, retrieves list of all protocol port objects with the protocol set to All.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/anyprotocolportobjects

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/anyprotocolportobjects/{object\_UUID}

Permissions: Object Manager

### **GET** applicationcategories

Request Type: GET

Description: Retrieves the application category object associated with the specified ID. If no ID is specified, retrieves list of all application category objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationcategories

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationcategories/{object\_UUID}

Permissions: Object Manager

#### **GET** applicationfilters

Request Type: GET

Description: Retrieves the application filter object associated with the specified ID. If no ID is specified, retrieves list of all application filter objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationfilters

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationfilters/{object\_UUID} Permissions: Object Manager

### **GET** applicationproductivities

Request Type: GET

Description: Retrieves the application productivity object associated with the specified ID. If no ID is specified, retrieves list of all application productivity objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationproductivities

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationproductivities/{object\_UUID}

Permissions: Object Manager

### **GET** applicationrisks

Request Type: GET

Description: Retrieves the application risk object associated with the specified ID. If no ID is specified, retrieves list of all application risk objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationrisks

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationrisks/{object\_UUID}

Permissions: Object Manager

#### **GET** applications

Request Type: GET

Description: Retrieves the application object associated with the specified ID. If no ID is specified, retrieves list of all application objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applications

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applications/{object\_UUID}

Permissions: Object Manager

### **GET** applicationtags

Request Type: GET

Description: Retrieves the application tag object associated with the specified ID. If no ID is specified, retrieves list of all application tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationtags

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationtags/{object\_UUID} Permissions: Object Manager

#### **GET** applicationtypes

#### Request Type: GET

Description: Retrieves the application type object associated with the specified ID. If no ID is specified, retrieves list of all application type objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationtypes

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationtypes/{object\_UUID} Permissions: Object Manager

#### **GET continents**

Request Type: GET

Description: Retrieves the continent object associated with the specified ID. If no ID is specified, retrieves list of all continent objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/continents

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/continents/{object\_UUID} Permissions: Object Manager

### **GET** countries

Request Type: GET

Description: Retrieves the country object associated with the specified ID. If no ID is specified, retrieves list of all country objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/countries

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/countries/{object\_UUID}

Permissions: Object Manager

#### **GET endpointdevicetypes**

#### Request Type: GET

Description: Retrieves the endpoint device type object associated with the specified ID. If no ID is specified, retrieves list of all endpoint device type objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/endpointdevicetypes

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/endpointdevicetypes/{object\_UUID}

Permissions: Object Manager

#### **GET** geolocation

Request Type: GET

Description: Retrieves the geolocation object associated with the specified ID. If no ID is specified, retrieves list of all geolocation objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/geolocations

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/geolocations/{object\_UUID} Permissions: Object Manager

### **DELETE** hosts

Request Type: DELETE

Description: Deletes the specified host object. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **PUT hosts**

Request Type: **PUT** Description: Modify a host object. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **POST** hosts

Request Type: **POST** Description: Create a host object with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts

Permissions: Object Manager>Modify Object Manager

### **GET** hosts

Request Type: GET

Description: Retrieves the host object associated with the specified ID. If no ID is specified, retrieves list of all host objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts/{object\_UUID} Permissions: Object Manager

#### **DELETE icmpv4objects**

Request Type: DELETE

Description: Deletes the specified ICMPv4 port. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv4objects/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **PUT icmpv4objects**

Request Type: **PUT** Description: Modify ICMPv4 port objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv4objects/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **POST icmpv4objects**

Request Type: POST

Description: Create ICMPv4 port objects with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv4objects Permissions: Object Manager>Modify Object Manager

### **GET** icmpv4objects

Request Type: GET

Description: Retrieves the ICMPv4 object associated with the specified ID. If no ID, retrieves list of all ICMPv4 objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv4objects

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv4objects/{object\_UUID}

Permissions: Object Manager

### **DELETE icmpv6objects**

Request Type: DELETE

Description: Deletes the specified ICMPv6 port objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv6objects/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **PUT** icmpv6objects

Request Type: **PUT** Description: Modify ICMPv6 port objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv6objects/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### POST icmpv6objects

Request Type: POST

Description: Create ICMPv6 port objects with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv6objects Permissions: Object Manager>Modify Object Manager

### **GET** icmpv6objects

Request Type: GET

Description: Retrieves the ICMPv6 object associated with the specified ID. If no ID is specified, retrieves list of all ICMPv6 objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv6objects

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/icmpv6objects/{object\_UUID} Permissions: Object Manager

### **GET** is esecurity group tags

Request Type: GET

Retrieves the ISE security group tag object with the specified ID. If no ID is specified, retrieves list of all ISE security group tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/isesecuritygrouptags

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/isesecuritygrouptags/{object\_UUID}

Permissions: Object Manager

#### **GET networkaddresses**

Request Type: **GET** Description: Retrieves list of all network and host objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networkaddresses Permissions: Object Manager

### **DELETE** networkgroups

Request Type: **DELETE** Description: Deletes the specified Network Group. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networkgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

#### PUT networkgroups

Request Type: **PUT** Description: Modify a Network Group. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networkgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

#### **POST** networkgroups

Request Type: **POST** Description: Create network group with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networkgroups Permissions: Object Manager>Modify Object Manager

#### **GET** networkgroups

#### Request Type: GET

Description: Retrieves the network group object associated with the specified ID. If no ID is specified, retrieves list of all network group objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networkgroups

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networkgroups/{object\_UUID}

Permissions: Object Manager

# **DELETE networks**

Request Type: **DELETE** Description: Deletes the specified network objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **PUT networks**

Request Type: **PUT** Description: Modify network objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **POST networks**

Request Type: POST

Description: Create network objects with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks Permissions: Object Manager>Modify Object Manager

### **GET** networks

Request Type: GET

Description: Retrieves the network objects associated with the specified ID. If no ID is specified, retrieves list of all network objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks/{object\_UUID} Permissions: Object Manager

# **DELETE** portobjectgroups

Request Type: **DELETE** Description: Deletes the specified port object groups. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/portobjectgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### PUT portobjectgroups

#### Request Type: PUT

Description: Modify port object groups. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/portobjectgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### POST portobjectgroups

Request Type: POST

Description: Create port object groups with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/portobjectgroups Permissions: Object Manager>Modify Object Manager

# **GET** portobjectgroups

Request Type: GET

Description: Retrieves the port object group object associated with the specified ID. If no ID is specified, retrieves list of all port object group objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/portobjectgroups URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/portobjectgroups/{object\_UUID} Permissions: Object Manager

# **GET** ports

Request Type: GET

Description: Retrieves list of all port objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ports Permissions: Object Manager

# **DELETE** protocolportobjects

#### Request Type: DELETE

Description: Deletes the specified protocol port objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/protocolportobjects/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **PUT** protocolportobjects

#### Request Type: PUT

Description: Modify protocol port objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/protocolportobjects/{object\_UUID}

Permissions: Object Manager>Modify Object Manager

# **POST** protocolportobjects

Request Type: POST

Description: Create protocol port objects with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/protocolportobjects

Permissions: Object Manager>Modify Object Manager

# **GET** protocolportobjects

Request Type: GET

Description: Retrieves the protocol port object associated with the specified ID. If no ID is specified, retrieves list of all protocol port objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/protocolportobjects URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/protocolportobjects/{object\_UUID} Permissions: Object Manager

# **DELETE ranges**

Request Type: DELETE

Description: Deletes the specified address range. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ranges/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **PUT ranges**

Request Type: PUT

Description: Modify a an address range. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ranges/{object\_UUID} Permissions: Object Manager>Modify Object Manager

#### **POST** ranges

#### Request Type: POST

Description: Create an address range with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ranges Permissions: Object Manager>Modify Object Manager

# **GET** ranges

Request Type: GET

Description: Retrieves the address range object associated with the specified ID. If no ID is specified, retrieves list of all address range objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ranges

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ranges/{object\_UUID} Permissions: Object Manager

# **GET realms**

Request Type: GET

Description: Retrieves the realm object associated with the specified ID. If no ID is specified, retrieves list of all realm objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/realms

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/realms/{object\_UUID}

Permissions: Object Manager

# **GET realmusergroups**

#### Request Type: GET

Description: Retrieves the realm user group object associated with the specified ID. If no ID is specified, retrieves list of all realm user group objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/realmusergroups

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/realmusergroups/{object\_UUID}

Permissions: Object Manager

Parameters available for filtering: realmUuid



**Note** This is a required parameter.

### **GET realmusers**

#### Request Type: GET

Description: Retrieves the realm user object associated with the specified ID. If no ID is specified, retrieves list of all realm user objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/realmusers

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/realmusers/{object\_UUID}

Permissions: Object Manager

Parameters available for filtering: realmUuid



This is a required parameter.

# **GET** securitygrouptags

Request Type: GET

Description: Retrieves the custom security group tag object associated with the specified ID. If no ID is specified, retrieves list of all custom security group tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securitygrouptags

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securitygrouptags/{object\_UUID}

Permissions: Object Manager

Parameters available for filtering: name

### **DELETE** securityzones

Request Type: DELETE

Description: Deletes the specified securityzone objects.

Permissions: Object Manager>Modify Object Manager

#### **PUT** securityzones

Request Type: **PUT** Description: Modifies a securityzone object. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **POST** securityzones

#### Request Type: POST

Description: Create securityzone objects with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones Permissions: Object Manager>Modify Object Manager

#### **GET** securityzones

Request Type: GET

Description: Retrieves the security zone objects associated with the specified ID. If no ID is specified, retrieves list of all security zone objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones/{object\_UUID}

Permissions: Object Manager

Parameters available for filtering: name

# **GET** siurlfeeds

Request Type: GET

Description: Retrieves the Security Intelligence url feed object associated with the specified ID. If no ID is specified, retrieves list of all Security Intelligence url feed objects.

URL: /api/fmc config/v1/domain/{domain UUID}/object/siurlfeeds

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/siurlfeeds/{object\_UUID} Permissions: Object Manager

# **GET** siurllists

Request Type: GET

Description: Retrieves the Security Intelligence url list object associated with the specified ID. If no ID is specified, retrieves list of all Security Intelligence url list objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/siurllists

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/siurllists/{object\_UUID}

Permissions: Object Manager

# **GET** tunneltags

Request Type: GET

Description: Retrieves the tunnel tag object associated with the specified ID. If no ID is specified, retrieves list of all tunnel tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/tunneltags

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/tunneltags/{object\_UUID} Permissions: Object Manager

### **GET urlcategories**

Request Type: GET

Description: Retrieves the url category object associated with the specified ID. If no ID is specified, retrieves list of all url category objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlcategories

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlcategories/{object\_UUID} Permissions: Object Manager

# **DELETE urlgroups**

Request Type: DELETE

Description: Deletes the specified urlgroup objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **PUT urlgroups**

Request Type: **PUT** Description: Modify urlgroup objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **POST urlgroups**

Request Type: **POST** Description: Create urlgroup objects with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlgroups Permissions: Object Manager>Modify Object Manager

# **GET urlgroups**

Request Type: GET

Description: Retrieves the url group objects associated with the specified ID. If no ID is specified, retrieves list of all url group objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlgroups

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urlgroups/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **DELETE urls**

Request Type: **GET** Description: Deletes the specified URL. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urls/{object\_UUID} Permissions: Object Manager

# **PUT** urls

Request Type: **PUT** Description: Modify a URL. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urls/{object\_UUID} Permissions: Object Manager

# **POST urls**

Request Type: **POST** Description: Create URLs with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urls Permissions: Object Manager

# **GET** urls

Request Type: **GET** Description: Retrieves the url objects associated with the specified ID. If no ID is specified, retrieves list of all url objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urls URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/urls/{object\_UUID} Permissions: Object Manager

# **GET variablesets**

Request Type: GET

Description: Retrieves the variable set object associated with the specified ID. If no ID is specified, retrieves list of all variable set objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/variablesets

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/variablesets/{object\_UUID} Permissions: Object Manager

#### **DELETE vlangrouptags**

Request Type: DELETE

Description: Deletes the specified vlangrouptag objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **PUT vlangrouptags**

Request Type: **PUT** Description: Modify vlangrouptag objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **POST vlangrouptags**

Request Type: **POST** Description: Create VLAN group tags with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags Permissions: Object Manager>Modify Object Managers

# **GET vlangrouptags**

#### Request Type: GET

Description: Retrieves the vlan group tag objects associated with the specified ID. If no ID is specified, retrieves list of all vlan group tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags/{object\_UUID}

#### Permissions: Object Manager>Modify Object Manager

# **DELETE vlantags**

Request Type: DELETE

Description: Deletes the specified VLAN tag objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID} Permissions: Object Manager>Modify Object Manager

# **PUT vlantags**

Request Type: **PUT** Description: Modify VLAN tag objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID} Permissions: Object Manager>Modify Object Manager

#### POST vlantags

Request Type: POST

Description: Create VLAN tags with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags Permissions: Object Manager>Modify Object Manager

# **GET vlantags**

Request Type: GET

Description: Retrieves the vlantag objects associated with the specified ID. If no ID is specified, retrieves list of all vlantag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID} Permissions: Object Manager

# **Policy Services**

# **DELETE** accesspolicies

Request Type: DELETE

Description: Deletes the access control policy with the specified ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{object\_UUID} Permissions: Policies>Access Control Policy>Modify Access Control Policy

## **PUT** accesspolicies

#### Request Type: PUT

Description: Modify an access control policy. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{object\_UUID} Permissions: Policies>Access Control Policy>Modify Access Control Policy

#### **POST** accesspolicies

Request Type: POST

Description: Create an access control policy with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies

Permissions: Policies>Access Control Policy>Modify Access Control Policy

# **GET** accesspolicies

Request Type: GET

Description: Retrieves the access control policy associated with the specified ID. If no ID is specified, retrieves a list of all access control policies.

URL: /api/fmc config/v1/domain/{domain UUID}/policy/accesspolicies

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{object\_UUID} Permissions: Policies

### **DELETE** accessrules

Request Type: **DELETE** 

Description: Delete an access control rule in the specified access control policy.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/accessrules/ {object\_UUID}

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

# **PUT** accessrules

Request Type: PUT

Description: Modify an access control rule in the specified access control policy.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/accessrules/ {object\_UUID}

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

#### **POST** accessrules

#### Request Type: POST

Description: Create an access control rule in the specified access control policy. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/accessrules Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

#### **GET** accessrules

Request Type: GET

Description: Retrieves the access control rule associated with the specified policy ID and rule ID. If no rule ID is specified, retrieves list of all access rules associated with the specified policy ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/accessrules

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/ accessrules/{object\_UUID}

Permissions: Policies>Access Control>Access Control Policy

# **PUT defaultactions**

Request Type: PUT

Description: Modifies the default action associated with the specified access control policy ID and default action ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/defaultactions/ {object\_UUID}

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

# **GET** defaultactions

Request Type: GET

Description: Retrieves the default action associated with the specified access control policy ID and default action ID. If no default action ID is specified, retrieves list of all default actions associated with the specified access control policy ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/defaultactions

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{container\_UUID}/ defaultactions/{object\_UUID}

Permissions: Policies>Access Control>Access Control Policy

### **GET** filepolicies

#### Request Type: GET

Description: Retrieves the file policy object associated with the specified ID. If no ID is specified, retrieves list of all file policy objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/filepolicies

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/filepolicies/{object\_UUID}

Permissions: Policies>Access Control>Malware & File Policy

### **GET** intrusionpolicies

#### Request Type: GET

Description: Retrieves the intrusion policy associated with the specified ID. If no ID is specified, retrieves list of all intrusion policies.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/intrusionpolicies

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/intrusionpolicies/{object\_UUID}

Permissions: Policies>Access Control>Intrusion Policy

### **GET** snmpalerts

Request Type: GET

Description: Retrieves the SNMP alert object associated with the specified ID. If no ID is specified, retrieves a list of all SNMP alert objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/snmpalerts

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/snmpalerts/{object\_UUID}

Permissions: Policies > Actions > Alerts > View Alerts

### **GET** syslogalerts

#### Request Type: GET

Description: Retrieves the syslog alert object associated with the specified ID. If no ID is specified, retrieves a list of all syslog alert objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/syslogalerts

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/syslogalerts/{object\_UUID}

Permissions: Policies > Actions > Alerts

# **Policy Assignment Services**

#### **PUT** policyassignments

#### Request Type: PUT

Description: Modify an assigned access policy to add a new device or a new device group. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments/{object\_UUID} Permissions:

# **POST** policyassignments

Request Type: **POST** 

Description: Assigns an unassigned access policy to devices or device groups. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments Permissions:

#### **GET** policyassignments

Request Type: GET

Description: Retrieves the policy assignment associated with the specified ID. If no ID is specified, retrieves a list of all policy assignments to target devices.

URL: /api/fmc config/v1/domain/{domain UUID}/assignment/policyassignments

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments/{object\_UUID}

Permissions:

Parameters available for filtering: name

# **Status Services**

# **GET** taskstatuses

Request Type: GET

Description: Retrieves information about a previously submitted pending job/task with the specified ID. This is currently supported for device registration and deployment jobs. If no ID is specified, retrieves list of all previously submitted pending Job/Tasks.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/job/taskstatuses

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/job/taskstatuses/{object\_UUID}

Permissions: Modify Devices/Deployment

# **System Information**

#### **GET** serverversion

Request Type: **GET** Description: Request version information for the server. URL: /api/fmc\_platform/v1/info/serverversion Permissions:

# Services Available in Firepower Threat Defense

# **GET physicalinterfaces**

Request Type: GET

Description: Retrieves the physical interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all physical interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/physicalinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ physicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management

# **GET redundantinterfaces**

Request Type: GET

Description: Retrieves the redundant interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all redundant interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ redundantinterfaces

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ redundantinterfaces/{object\_UUID}

Permissions: Devices > Device Management

### **GET** etherchannelinterfaces

#### Request Type: GET

Description: Retrieves the ethernet channel interface associated with the specified NGFW device ID and interface ID. If no ID is specified, retrieves list of all ethernet channel interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ etherchannelinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ etherchannelinterfaces/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering:

# **GET** subinterfaces

#### Request Type: GET

Description: Retrieves the sub-interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all sub-interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/subinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/ subinterfaces/{object\_UUID}

Permissions: Devices > Device Management

# **GET** bridgegroupinterfaces

Request Type: GET

Description: Retrieves the bridge group interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all bridge group interfaces associated with the specified NGFW device ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ bridgegroupinterfaces

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/ bridgegroupinterfaces/{object\_UUID}

Permissions: Devices > Device Management

# **POST devicerecords**

#### Request Type: POST

Description: Registers the specified device to the Firepower Managemenr Center. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords Permissions: Devices > Device Management > Modify Devices

# **PUT** devicerecords

Request Type: PUT

Description: Modifies the device record associated with the specified ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

# **GET devicegrouprecords**

Request Type: GET

Description: Retrieves the device group associated with the specified ID. If no ID is specified, retrieves list of all device groups.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID}

Permissions: Devices > Device Management > View Devices

# **DELETE devicerecords**

Request Type: DELETE

Description: Unregisters the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID}

Permissions: Devices > Device Management > Modify Devices

### POST devicegrouprecords

Request Type: POST

Description: Create a device group with the specified object ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords Permissions: Devices > Device Management > Modify Devices

### **PUT devicegrouprecords**

Request Type: PUT

Description: Modifies a device group with the specified object ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

#### **GET devicegrouprecords**

#### Request Type: GET

Description: Retrieves the device group associated with the specified ID. If no ID is specified, retrieves list of all device groups.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID}

Permissions: Devices > Device Management > View Devices

### **DELETE devicegrouprecords**

Request Type: DELETE

Description: Deletes a device group with the specified object ID. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID} Permissions: Devices > Device Management > Modify Devices

# **POST securityzones**

Request Type: POST

Description: Create securityzone objects with the specified parameters. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones Permissions: Object Manager>Modify Object Manager

### **PUT** securityzones

Request Type: PUT

Description: Modifies a securityzone object. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **GET** securityzones

Request Type: GET

Description: Retrieves the security zone objects associated with the specified ID. If no ID is specified, retrieves list of all security zone objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones/{object\_UUID}

Permissions: Object Manager Parameters available for filtering: name

# **DELETE** securityzones

Request Type: DELETE

Description: Deletes the specified securityzone objects. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/securityzones/{object\_UUID} Permissions: Object Manager>Modify Object Manager

### **POST** policyassignments

Request Type: POST

Description: Assigns an unassigned access policy to devices or device groups. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments Permissions:

# **PUT policyassignments**

Request Type: PUT

Description: Modify an assigned access policy to add a new device or a new device group. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments/{object\_UUID} Permissions:

# **GET** policyassignments

Request Type: GET

Description: Retrieves the policy assignment associated with the specified ID. If no ID is specified, retrieves a list of all policy assignments to target devices.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/assignment/policyassignments/{object\_UUID}

Permissions:

Parameters available for filtering: name

## **GET** deployabledevices

Request Type: GET

Description: Retrieves list of all devices with configuration changes, ready to be deployed.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/deployment/deployabledevices Permissions: Deploy Configuration to Devices Parameters available for filtering: name

# **POST deploymentrequests**

#### Request Type: POST

Description: Creates a request for deploying configuration changes to the specified device. URL: /api/fmc\_config/v1/domain/{domain\_UUID}/deployment/deploymentrequests/{object\_UUID} Permissions: Deploy Configuration to Devices